–Download **Adaptio IPDS Print Server Software** at the following URL:

http://www.iocorp.com/adaptio-download as shown below:



Adaptio IPDS Print Server Software **requires .NET Framework 3.5 to be installed**.
The image below is the error you will receive if .NET Framework 3.5 is not "turned on".



Adaptio IPDS Print Server Software **requires .NET Framework 3.5 to be installed**.

If you are unsure if this version of the .NET Framework is installed do the following:

Go to Control Panel and locate **"Programs and Features"** as shown below



Click on **"Programs and Features"** to bring up the screen below. Locate **"Turn Windows features on or off"** and click on it. The screen on the next page will appear.



The **"Windows Features**" window will indicate if **.NET Framework 3.5** is turned on or off.
if the box in front of **.NET Framework 3.5 is selected as shown below**, it is turned on. If it is blank, it is not enabled.
Select this box and then click OK. This will **turn on** .NET Framework 3.5



The image below is the error you will receive if .NET Framework 3.5 is not "turned on".



After installing the Adaptio Software you will see the window below once it is started.

This is the **"Adaptio Management"** window.

You will find this by **pressing the Windows Start button** in the lower left corner of the screen. Once you locate **"I-O Adaptio Print Server"** in your apps list, **click on it** and **then select "Adaptio Management".**







This is simply a **verbal description** of the printer, location, etc., for example "**Test Printer".** This is not the AS/400 Printer Name.

You will need to **configure an IPDS Printer Session** on the AS/400 using **the IP Address of the PC** on which Adaptio is installed **as the IP address of the IPDS Printer.**

IP Port Number. Needed for the **Device Description** on the AS/400

If you have a **network printer** you would like to use, you do so by simply entering its **IP Address** and leaving the "Windows Printer" section blank.

Simply Select the **Windows Printer Driver** for the **Printer connected to this PC** (the one on which Adaptio is installed) you want to use as "Test Printer", the printer you want the AS/400 to see as your IPDS printer.

This '**Windows Printer**" can either be physically attached to the PC or a network printer configured on it.

Information Needed for Creating your IPDS Printer "Device Description" on the AS/400:

1. **IP Port Number** – as shown above diagram
2. **IP Address** – **IP address of the PC** on which Adaptio IPDS Print Server Software is installed (NOT the IP address of the network printer you want to have IPDS printing capability).
3. **PSFCFG Name** – you can use one you are currently using for other IPDS Printers.

PLEASE NOTE: You can see the attached IBM document regarding IPDS Device Configuration and PSF Configurations if you need additional information on performing these tasks.